

Polar HRM2 File Format Description



Polar HRM2 File Format Description

Contents

| 1. | GENERAL INFORMATION | 1 |
|-----|--------------------------|---|
| | GENERAL PARAMETERS | |
| | POLAR COACH PARAMETERS | |
| | | |
| | EXERCISE NOTE | |
| | HR ZONES | |
| 6. | HR LIMIT SWAPS | ţ |
| 7. | HR/CC MODE SWAPS | ţ |
| 8. | LAP TIMES | į |
| 9. | LAP TIME NOTES | ţ |
| 10. | EXTRA DATA SERIES | ţ |
| 11. | HR LIMIT SUMMARY | |
| 12. | HR THRESHOLD SUMMARY | |
| 13. | CYCLING PARAMETERS | • |
| | HEART RATE DATA | |
| | | • |
| 15 | FXTENDED HEART RATE DATA | |



1. General Information

The following Polar HRM file format is used in Polar software products. The data includes the exercise information transferred from the following Polar products:

- Polar Sport Tester (PST)
- Polar Vantage XL (VXL)
- Polar Vantage NV (VNV)
- Polar Accurex Plus (Acc+)
- Polar XTrainer Plus (XTr+)
- Polar Coach
- Polar S610 / S610i / S625X
- Polar S710 / S710i / S720i / S725 / S725X
- Polar S810 / S810i
- Polar E600
- Polar AXN500, Polar AXN700

For further information about HR monitor specific features, see HR monitor user's manuals. Make sure to handle the HRM file version number correctly. Version modifications are marked with * and *.

The data is stored in ASCII format. CR and LF (0Dh and 0Ah) at the end of each line. There is one empty line between each data section. The data section name is separated from actual data always with brackets [].

2. General Parameters

| DATA | COMMENTS |
|-------------|----------------------------------------------------------------------|
| [Params] | Basic settings |
| Version=107 | Exact hrm file version (1.02, 1.05*, 1.06*, 1.07 ^{&}). |
| Monitor=1 | Heart rate monitor type |
| | 1 = Polar Sport Tester / Vantage XL |
| | 2 = Polar Vantage NV (VNV) |
| | 3 = Polar Accurex Plus |
| | 4 = Polar XTrainer Plus |
| | 6 = Polar S520 |
| | 7 = Polar Coach |
| | 8 = Polar S210 |
| | 9 = Polar S410 |
| | 10 = Polar S510 |
| | 11 = Polar S610 / S610i |
| | 12 = Polar S710 / S710i / S720i |
| | 13 = Polar S810 / S810i |
| | 15 = Polar E600 |



```
20 = Polar AXN500
                                     21 = Polar AXN700
                                     22 = Polar S625X / S725X
                                     23 = Polar S725
Mode=110
                              Data types:
(abc)
                                     a) Cad/Alt:
With versions \rightarrow 1.05
                                            0 = Cad, 1 = Alt, 3 = None
                                     b) CC data
                                            0 = HR data only, 1 = HR + cycling data
                                     c) US / Euro unit
                                            0 = Euro (km, km/h, m)
                                            1 = US (miles, mph, ft)
                              All distance, speed and altitude values depend on US/Euro unit selection (km / miles,
                              km/h / mph, m / ft).
SMode=11011010
                              Data type parameters
(abcdefgh)
                              a) Speed (0=off, 1=on)
With versions 1.06
                              b) Cadence (0=off, 1=on)
                              c) Altitude (0=off, 1=on)
SMode=110110100
                              d) Power (0=off, 1=on)
                              e) Power Left Right Balance (0=off, 1=on)
(abcdefahi)
With versions 1.07 →
                              f) Power Pedalling Index (0=off, 1=on)
                              g) HR/CC data
                                    0 = HR data only, 1 = HR + cycling data
                              h) US / Euro unit
                                    0 = Euro (km, km/h, m, °C)
                                    1 = US (miles, mph, ft, °F)
                                    All distance, speed, altitude and temperature values depend on US/Euro unit
                                    selection (km / miles, km/h / mph, m / ft, °C / °F).
                              i) Air pressure (0=off, 1=on) &
Date=20040831
                              Date of exercise (yyyymmdd)
                              For example 20040831means 31st August 2004)
StartTime=14:23:36.0
                              Start time (hh:mm:ss.d)
                              If hours are less than 10, format h:mm:ss.d have also been used. Check time format by
                              checking: character.
Length=00:30:00.4
                              Length of exercise (hh:mm:ss.d)
                              If hours are less than 10, format h:mm:ss.d have also been used. Check time format by
                              checking: character.
Interval=5
                              Data type:
                                       5
                                                 5 seconds recording interval
                                      15
                                            = 15 seconds recording interval
                                      30
                                            = 30 seconds recording interval
                                      60
                                            = 60 seconds recording interval
                                            = 120 seconds recording interval (dynamic)
                                     120
                                     240
                                            = 240 seconds recording interval (dynamic)
                                     300
                                            = 5 minutes recording interval
                                     480
                                            = 480 seconds recording interval (dynamic)
                                     238
                                            = R - R data (VNV, S810, S810i)
                                     204
                                            = intermediate times only
                                               (PST, VXL, VNV, XTr+, Acc+)
```



29.03.06 Version 1.3

Polar HRM2 File Format Description

Page 5 (12)

| Upper1=160 | Upper limit 1 (bpm) |
|----------------|-------------------------------------------------------------------|
| Lower1=80 | Lower limit 1 (bpm) |
| Upper2=160 | Upper limit 2 (bpm) |
| Lower2=80 | Lower limit 2 (bpm) |
| Upper3=160 | Upper threshold / Upper limit 3 (bpm) |
| Lower3=80 | Lower threshold / Lower limit 3 (bpm) |
| Timer1=00:00 | Exercise timer 1 (mm:ss) |
| Timer2=00:00 | Exercise timer 2 (mm:ss) |
| Timer3=00:00 | Exercise timer 3 (mm:ss) |
| ActiveLimit=0 | Limits in use in "File Summary": |
| | 0 = Limits 1 and 2, 1 = Treshold limits |
| MaxHR=195 | Personal max heart rate (bpm) |
| RestHR=52 | Personal resting heart rate (bpm) |
| StartDelay=300 | RR Start delay (ms) (Vantage NV RR data only) |
| VO2max=50 | VO2max at time of exercise (for calories calculation) ml/min/kg # |
| Weight=75 | Weight at time of exercise (for calories calculation) kg# |

3. Polar Coach Parameters

| DATA | | | COMMENTS |
|---------|------|----|------------------------------------------------------------|
| [Coach] |] | | Polar Coach data section |
| 000128 | } | | Coach flag data in bit fields |
| 0 | 0 | | Recovery data; result HR, result time (in seconds) |
| 0 | 0 | | Interval data; HR average, interval time (in seconds) |
| 0 | 1175 | 26 | Target zone 1 data; (below tz, in tz, above tz) in seconds |
| 0 | 0 | 0 | Target zone 2 data; (below tz, in tz, above tz) in seconds |
| 0 | 0 | 0 | Target zone 3 data; (below tz, in tz, above tz) in seconds |
| 128 | 164 | | Average Hr of the exercise, maximum Hr of the exercise |

Flags 8 - bits are in use, (87654321), rest of the bits are reserver for future needs

8 bit, 1 = recovery not used

7 bit, 1 = negative recovery

6 bit, 1 = recording in continious interval mode

5 bit, 1 = interval mode used during recording

4 bit, 1 = time recovery calculation enabled during recording

3 bit, 1 = HR recovery calculation enabled during recording

2 bit, 1 = Limit 3 enabled during recording

1 bit, 1 = Limit 2 enabled during recording

Note: Coach parameters are only from Polar Coach HR monitor.



4. Exercise Note

| DATA | COMMENTS |
|--------|--------------------------|
| [Note] | Notes |
| Note! | Max 250 ASCII characters |

5. HR Zones

| DATA | COMMENTS |
|-----------|-----------------------------------------------|
| [HRZones] | Heart rate zones used for this exercise |
| 190 | Zone 1 upper limit (bpm) |
| 180 | Zone 2 upper limit (bpm) = Zone 1 lower limit |
| 170 | Zone 3 upper limit (bpm) |
| 160 | Zone 4 upper limit (bpm) |
| 150 | Zone 5 upper limit (bpm) |
| 140 | Zone 6 upper limit (bpm) |
| 0 | Zone 7 upper limit (bpm) |
| 0 | Zone 8 upper limit (bpm) |
| 0 | Zone 9 upper limit (bpm) |
| 0 | Zone 10 upper limit (bpm) |
| 0 | Zone 10 lower limit (bpm) |

6. HR Limit Swaps

| DATA | | COMMENTS |
|-------------|---|-----------------------------------------------------------------------------------------------------------------------------------------|
| [SwapTimes] | | Time when HR limits have been swapped between limits 1 2 and 3. By default the limits 1 are starting limits. Limit index is zero-based. |
| 00:10:00.0 | 1 | Time when limits have been changed to limits 2 |
| 00:20:00.0 | 2 | Time when limits have been changed to limits 3 |
| 00:30:00.0 | 0 | Time when limits have been changed to limits 1 |

7. HR/CC Mode Swaps

HR/CC mode swaps are available only with Polar XTrainer Plus.

| DATA | | COMMENTS |
|--------------|----|------------------------------------------------------------------------------------------|
| [HRCCModeCh] | | Mode change |
| 00:00:0.0 32 | | HR to CC (The change from HR measurement to cycling measurement mode at time hh:mm:ss.d) |
| 00:05:54.7 | 16 | CC to HR |



| DATA | | | COM | MENTS | | | |
|------------|------|-----|-----|-------|-----|--------------------|--|
| [IntTimes] | | | | | | Lap times | |
| 00:03:4 | 43.7 | 123 | 100 | 150 | 200 | Row 1 | |
| 32 | 0 | 0 | 0 | 0 | 0 | Row 2 Lap time 0 | |
| 0 | 0 | 0 | 0 | 0 | | Row 3 | |
| 0 | 400 | 455 | 21 | 0 | 0 | Row 4 [#] | |
| 0 | 0 | 0 | 0 | 0 | 0 | Row 5 [#] | |
| 00:04: | 54.7 | 159 | 130 | 170 | 200 | Row 1 | |
| 32 | 0 | 0 | 0 | 0 | 0 | Row 2 Lap time 1 | |
| 0 | 0 | 0 | 0 | 0 | | Row 3 | |
| 0 | 400 | 470 | 21 | 0 | 0 | Row 4 [#] | |
| 0 | 0 | 0 | 0 | 0 | 0 | Row 5 [#] | |

Field descriptions:

| 1 1014 400011 | | | * | | | |
|---------------|--------|--------|--------|------|-----|--------------------|
| [IntTimes] | | | | | | Lap times |
| Time | HR | HR | HR | HR | | Row 1 |
| | | min | avg | max | | |
| Flags | Rec. | Rec. | Speed | Cad | Alt | Row 2 |
| | Time | HR | | | | |
| Extra1 | Extra2 | Extra3 | Asc | Dist | | Row 3 |
| Lap type | Lap | Power | Tempe | Phas | 0 | Row 4 [#] |
| | Dist | | rature | eLap | | |
| 0 | 0 | 0 | 0 | 0 | | Row 5 [#] |

| R٥ | W | 1 |
|---------------------|----|---|
| $\cdot \cdot \cdot$ | vv | |

Time Lap time in format hh:mm:ss.d HR Momentary heart rate value in bpm HR min Lap's minimum heart rate value in bpm Lap's average heart rate value in bpm HR avg HR max Lap's maximum heart rate value in bpm

Row 2

Flags Misc lap time information in 8 bits, 87654321

bit 8 = Polar Coach lap/interval flag (0 = lap, 1 = interval)

bit 7 = Int. time erased (for conconi test, not included to calculation)

bit 6 = Int. type (0 = fixed, 1 = from hrm)bit 5 = Extra data 3 (1 = selected to draw) bit 4 = Extra data 2 (1 = selected to draw) bit 3 = Extra data 1 (1 = selected to draw)

bits 1,2 = Recovery (0 = no rec, 1 = Time rec, 2 = HR rec)

Rec. Time Recovery time (seconds) Rec. HR Recovery HR (bpm)

Speed Momentary speed in Xtrainer units (km/h or mph = X/128)



29.03.06
Version 1.3
Polar HRM2 File Format Description

Page 8 (12)

Cad Momentary cadence (rpm)

Alt Momentary altitude (HRM version 1.02: 10m / 10ft, version 1.05 → 1m/1ft)*

Row 3

Extra 1 - 3 Values of extra data series (0 - 3000) (the actual value is multiplied by ten)

Asc Lap ascent value from XTr+ 10m / 10ft
Dist Lap distance value from XTr+ 0.1km / 0.1ft

Row 4[#]

Lap type Lap type identifier, replaces flag 8 (Polar Coach lap/interval flag) value

| Туре | Description | Туре | Description |
|------|---------------------|--------|-----------------|
| 0 | normal lap | 8192 | end of exercise |
| 1 | interval | 16384 | off road |
| 2 | start of exercise | 32768 | road |
| 4 | finishing line | 65536 | head wind |
| 8 | uphill | 131072 | tail wind |
| 16 | downhill | 262144 | Score / goal |
| 32 | service | 524288 | penalty |
| 64 | stopped | | |
| 128 | orienteering marker | | |
| 256 | u-turn | | |
| 512 | summit / peak | | |
| 1024 | sprint | | |
| 2048 | crash | | |
| 4096 | timeout | | |

Lap Dist Manually given lap distance in meters / yards, units are depending on

US/Euro unit selection

Power Momentary power value in Watts

Temperature Momentary temperature value in Celcius / Fahrenheit, units are depending

on US/Euro unit selection (temperature automatically only from S710)

PhaseLap Internal phase/lap information used for interval calculation

The rest of the new lap time parameters are reserved for future usage. Lap times were fromerly known as Intermediate times.

9. Lap Time notes

| DA | TA | COMMENTS |
|------------|----------------|--------------------------------------|
| [IntNotes] | | Intermediate time note texts |
| 3 | Traffic lights | Third intermediate time's note text. |
| 5 | Interval | Fifth intermediate time's note text. |



10. Extra Data Series

| DATA | | COMMENTS |
|-------------|---|-------------------------------------------|
| [ExtraData] | | Extra data names and units (max 3 series) |
| Lactate | | Extra data 1 name |
| mmol/l 15 | 0 | Extra data 1 unit, max value, min value |
| Power | | Extra data 2 name |
| W 2000 | 0 | Extra data 2 unit, max value, min value |

11. HR Limit Summary

| DATA | | | | | | COMMENTS |
|-------|---------------|----|------|----|--------------|-----------------------------------|
| [Sumi | [Summary-123] | | | | File summary | |
| 3780 | 10 | 40 | 3700 | 30 | 0 | Summary for limits 1 (row 1) |
| 195 | 160 | 80 | 52 | | | Limit values for limits 1 (row 2) |
| 0 | 0 | 0 | 0 | 0 | 0 | Summary for limits 2 (row 1) |
| 195 | 160 | 80 | 52 | | | Limit values for limits 2 (row 2) |
| 0 | 0 | 0 | 0 | 0 | 0 | Summary for limits 3 (row 1) |
| 195 | 160 | 80 | 52 | | | Limit values for limits 3 (row 2) |
| 0 | 756 | • | | | | 756 x 5 secs/sample = 3780 sec |
| | | | | | | Maximum of 20 selections/file |

Row 1

3780 = Total time for selection in seconds (=10+40+3700+30+0)

10 = Time in seconds when the HR was above maximum

40 = Time in seconds when the HR was between UL1 and maximum

3700 = Time in seconds when the HR was between UL1 and LL1

30 = Time in seconds when the HR was between LL1 and rest HR

0 = Time in seconds below rest HR

Row 2

195 = Max. HR

160 = Upper limit 1

80 = Lower limit 1

52 = Rest HR

Summary information for limits 2 and 3 follow the same pattern.

The row of selection

0 = Selection start sample

756 = Selection end sample



12. HR Threshold Summary

| DATA | | | | COMMENTS | | |
|------------------|------------------|----------|------------|----------|---|---------------------------------------------------------------------------------------------------------------------------------------|
| [Summary-TH] | | | | | | |
| 3780 195 0 | 10 160 756 | 40 80 | 3700 52 | 30 | 0 | Summary for threshold limits (row 1) Limit values for th. limits (row 2) 756 x 5 secs/sample = 3780 sec Maximum of 20 selections/file |

Row 1

3780 = Total time for selection in seconds (=10+40+3700+30+0)

10 = Time in seconds when the HR was above maximum

= Time in seconds when the HR was between upper TH and maximum

3700 = Time in seconds when the HR was between lower and upper TH

30 = Time in seconds when the HR was lower TH and rest HR

0 = Time in seconds below rest HR

Row 2

195 = Maximum HR

160 = Upper (anaerobic) threshold

80 = Lower (aerobic) threshold

= Resting HR

Row 3

0 = Selection start sample

756 = Selection end sample

13. Cycling Parameters

Cycling parameters are available from XTr+, S710, S710i, S720i, S725.

| DATA | COMMENTS |
|--------|---------------------------------------------------------------|
| [Trip] | Cycling trip data |
| 87 | Distance = 8,7 km / mile |
| 1400 | Ascent (hrm 1.02 10m / 10ft, hrm 1.05 → 1m / 1ft) * |
| 92982 | Total time in seconds |
| 1159 | Average altitude (HRM 1.02 10m / 10ft, HRM 1.05→ 1m / 1ft) * |
| 1304 | Maximum altitude (HRM 1.02 10m / 10ft, HRM 1.05 → 1m / 1ft) * |
| 1882 | Average speed = 1882 / 128 = 14,7 km/h / mph |
| 3396 | Maximum speed = 3396 / 128 = 26,5 km/h / mph |
| 418 | Odometer value at the end of an exercise, 418 = 418 km / mile |



14. Heart Rate Data

The following data format is valid when there is only heart rate information in exercise file.

| The following data formatio valid when there is only heart fate information in exercise me. | | | | | | |
|---------------------------------------------------------------------------------------------|-------------------------------------------------------------------|--|--|--|--|--|
| DATA | COMMENTS | | | | | |
| [HRData] | Heart rate data | | | | | |
| 83 | Heart rate | | | | | |
| 86 | When the recording interval is 5,15, 60, seconds, the value of | | | | | |
| 85 | the heart rate is between 0 and 250 bpm. | | | | | |
| 94 | When the recording interval (=data type) is 238 (=R-R), the value | | | | | |
| 103 | is R-R interval in milliseconds (=>HR[bpm] = 60000/RR). | | | | | |
| 106 | When the interval is 204 (= int times only), there are no | | | | | |
| 107 | values, only the header "[HRData]". | | | | | |

15. Extended Heart Rate Data

The following data format is for HRM versions \rightarrow 1.05

| DATA | COMMENTS | | |
|-------------------|------------------|---------------------------|--|
| [HRData] | Speed | Cadence (rpm) or Altitude | |
| Heart Rates (bpm) | (0.1 km/h / mph) | (m/ft, see below) | |
| | | (optional field) | |
| 86 | 161 | 770 | |
| 94 | 165 | 770 | |
| 107 | 118 | 770 | |
| 108 | 126 | 790 | |

Values are separated by tab characters.

Speed: If US units are used, speed value 165 means 16.5 mph. If Euro units are used, speed value 165 means 16.5 km/h.

Altitude: Altitude values with hrm version 1.02 in format 10m / 10ft (to get correct value, multiply the altitude value by ten) and with hrm version 1.05 in format 1m / 1ft *

Cadence: The cadence field is optional and available only when cadence was recorded into exercise file. The availability of cadence is saved into Mode=... (→ v1.05, a) Cad/Alt = 1).

Air pressure: The air pressure field is optional and available only when air pressure was recorded into file. Air pressure can be saved with Polar AXN500 and AXN700 outdoor computers.





The following data format is for HRM version 1.06→

| DATA | COMMENTS | | | | |
|-------------|--------------------|---------|----------------|-------|---------------|
| [HRData] | Speed | Cadence | Altitude | Power | Power Balance |
| Heart Rates | (0.1 km/h or (rpm) | | (m/ft) (Watts) | | and Pedalling |
| (bpm) | mph) | | | | Index |
| 83 | 173 | 81 | 760 | 325 | 12857 |
| 85 | 171 | 90 | 780 | 340 | 12857 |
| 94 | 165 | 92 | 770 | 335 | 12857 |

The following data format is for HRM version 1.07 \rightarrow

| DATA | COMMENTS | | | | | |
|-------------|--------------|---------|----------|---------|---------------|----------|
| [HRData] | Speed | Cadence | Altitude | Power | Power Balance | Air |
| Heart Rates | (0.1 km/h or | (rpm) | (m/ft) | (Watts) | and Pedalling | pressure |
| (bpm) | mph) | | | | Index | |
| 83 | 173 | 81 | 760 | 325 | 12857 | 1004 |
| 85 | 171 | 90 | 780 | 340 | 12857 | 1003 |
| 94 | 165 | 92 | 770 | 335 | 12857 | 1003 |

The cycling data fields are optional and are available if exercise contains cycling data. The SMode field at [Params] section describes the data available.

- Speed is available if SMode a=1
- Cadence is available if SMode b=1
- Altitude is available if SMode c=1
- Power (watts) is available if SMode d=1
- Power (LRB and PI) are available if SMode e=1
- Air pressure is available if SMode i=1

Power LRB + PI: The second power value contains Left Right Balance (LRB) and Pedalling Index (PI) values in the following formula:

LRB is the value of left foot \rightarrow for example if LRB = 45, actual balance is L45 - 55R. PI values are percentages from 0 to 100. For example value 12857 (= 40 * 256 + 47) means: PI = 40 and LRB = 47 => L47 - 53R